



AUBO-i5 Robot Python interface

Original Version 1.0

AUBO (Beijing) Robotics Technology Co., Ltd.

Table of contents

1. Import the interface library and instantiate the robot control object	3
2. Initialization (static method)	3
3. Deinitialization (static method)	3
4. Create the control context handle	3
5. Remove the control context handle	4
6. Robot system login	4
7. Robot system logout	4
8. Initialize the global properties of the robot control	4
9. Set the maximum acceleration of each joint	5
10. Get the maximum joint acceleration of the robot	5
11. Set the maximum velocity of each joint	5
12. Get the maximum velocity of each joint	6
13. Set the maximum linear acceleration of the robot end	6
14. Get the maximum linear acceleration of the robot end	6
15. Set the maximum linear velocity of the robot end	7
16. Get the maximum linear velocity of the robot end	7
17. Set the maximum angular acceleration of the robot end	7
18. Get the maximum angular acceleration of the robot end	8
19. Set the maximum angular velocity of the robot end	8
20. Get the maximum angular velocity of the robot end	8
21. The joint movement of the robot	9
22. The Linear movement of the robot	9
23. Remove all the set global waypoints	9
24. Add the global waypoint for track movement	10
25. The track movement of the robot	10
26. Set the blend radius	11
27. Set the times of the circular movement	11
28. Set the user coordinate system	12
29. Set the base coordinate system	13
30. Check whether the user coordinate is reasonable	13
31. Set the relative offset on base coordinate system	14
32. Set the relative offset on user coordinate system	14
33. Forward kinematics	15
34. Inverse kinematics	15
35. Convert the base coordinate system to user coordinate system	16
36. Convert the user coordinate system to base coordinate system	17
37. Robot startup	18
38. Shut down the robot	18

39. Stop the robot movement	19
40. Suspend the robot movement.....	19
41. Continue the movement of robot	19
42. Collision recovery	20
43. Get the service state of the robot	21
44. Set the working mode of the robot	21
45. Get the current working mode of the robot.....	21
46. Set the collision class of the robot.....	22
47. Determine whether the real robot has been linked	22
48. Get the joint state of the real robot	22
49. Get the I/O configuration of the robot interface board.....	23
50. Set the I/O state of the robot interface board.....	24
51. Get the I/O state of the robot interface board	25
52. Get the tool power state of the robot.....	25
53. Set the tool power state of the robot	26
54. Set the tool I/O type of the robot	26
55. Get the tool power value of the robot	26
56. Set the tool I/O state of the robot.....	27
57. Set the tool I/O state of the robot.....	27
58. The robot event callback function	28

1. Import the interface library and instantiate the robot control object

```
from robotcontrol import *
robot = Auboi5Robot()
```

2. Initialization (static method)

Name:	Auboi5Robot.initialize()
Function:	Dynamic library initialization
Parameters:	
Returns:	Success: 0
	Fail: other

3. Deinitialization (static method)

Name:	Auboi5Robot.uninitialize()
Function:	Dynamic library initialization
Parameters:	
Returns:	Success: 0
	Fail: other

4. Create the control context handle

Name:	create_context()
Function:	Create the control context handle
Parameters:	
Returns:	Success: context handle RSHD >= 0
	Fail: -1

5. Remove the control context handle

Name:	destory_context(RSHD)
Function:	Remove the control context handle
Parameters:	RSHD context handle
Returns:	Success: 0
	Fail: other

6. Robot system login

Name:	login(IP, PORT)
Function:	Login robot system
Parameters:	IP robot IP address PORT robot port number
Returns:	Success: 0
	Fail: other

7. Robot system logout

Name:	logout()
Function:	Logout robot system
Parameters:	RSHD context handle
Returns:	Success: 0
	Fail: other

8. Initialize the global properties of the robot control

Name:	init_profile()
Function:	Initialize the global properties of the robot control
Parameters:	
Returns:	Success: 0
	Fail: other

9. Set the maximum acceleration of each joint

Name:	set_joint_maxacc(joint_maxacc=(1.0,1.0,1.0,1.0,1.0,1.0))
Function:	Set the maximum acceleration for robot
Parameters:	Acc is the joint acceleration, unit: rad/s
Returns:	Success: 0
	Fail: other

10. Get the maximum joint acceleration of the robot

Name:	get_joint_maxacc()
Function:	Get the maximum joint acceleration of the robot
Parameters:	Acc is the joint acceleration of six joints, unit: rad/s
Returns:	Success: the maximum acceleration of six joints, unit: rad/s
	Fail: None

11. Set the maximum velocity of each joint

Name:	set_joint_maxvelc(joint_maxvelc=(1.0,1.0,1.0,1.0,1.0,1.0))
Function:	Set the maximum velocity for robot
Parameters:	Acc is the joint velocity of six joints, unit: rad/s
Returns:	Success: 0
	Fail: other

12. Get the maximum velocity of each joint

Name:	get_joint_maxvelc()
Function:	Get the maximum velocity for robot
Parameters:	velc is the joint velocity of six joints, unit: rad/s
Returns:	Success: the maximum velourity of six joints, unit: rad/s Fail: None

13. Set the maximum linear acceleration of the robot end

Name:	set_end_max_line_acc(end_maxacc=0.1)
Function:	Set the acceleration for robot end
Parameters:	end_maxacc is the end side acceleration, unit: meter per sec
Returns:	Success: 0 Fail: other

14. Get the maximum linear acceleration of the robot end

Name:	get_end_max_line_acc()
Function:	Get the acceleration for robot end
Parameters:	
Returns:	Success: the maximum acceleration of the robot end, unit(m/s) Success: 0 Fail: None

15. Set the maximum linear velocity of the robot end

Name:	set_end_max_line_velc(end_maxvelc=0.1)
Function:	Set the maximum linear velocity of the robot end
Parameters:	end_maxacc : the maximum velocity for end side, unit(m/s)
Returns:	Success: 0
	Fail: other

16. Get the maximum linear velocity of the robot end

Name:	get_end_max_line_velc()
Function:	Get the maximum linear velocity of the robot end
Parameters:	
Returns:	Success: the maximum velocity of the robot end, unit(m/s)
	Fail: None

17. Set the maximum angular acceleration of the robot end

Name:	set_end_max_angle_acc(end_maxacc=0.1)
Function:	Set the acceleration for robot end
Parameters:	end_maxacc : the maximum end side acceleration, unit: rad/s
Returns:	Success: 0
	Fail: other

18. Get the maximum angular acceleration of the robot end

Name:	get_end_max_angle_acc()
Function:	Get the maximum end side acceleration of the robot
Parameters:	
Returns:	Success: the maximum of the robot end , unit: rad/s
	Fail: None

19. Set the maximum angular velocity of the robot end

Name:	set_end_max_angle_velc(end_maxvelc=0.1)
Function:	Set the velocity for robot end
Parameters:	end_maxacc: the maximum end side velocity, unit: rad/s
Returns:	Success: 0
	Fail: other

20. Get the maximum angular velocity of the robot end

Name:	get_end_max_angle_velc()
Function:	Get the maximum end side velocity of the robot
Parameters:	
Returns:	Success: the maximum velocity of the robot end, unit: rad/s
	Fail: None

21. The joint movement of the robot

Name:	move_joint(joint_radian=(0.000000,0.000000,0.000000,0.000000,0.000000,0.000000))
Function:	The joint movement of the robot
Parameters:	Joint_radian: the joint angle of six joints, unit: radian
Returns:	Result:
	Success: RobotErrorType.RobotError_SUCC

22. The Linear movement of the robot

Name:	move_line(joint_radian(1.0,1.0,1.0,1.0,1.0,1.0))
Function:	The robot linearly moves to target position form the current position
Parameters:	RSHD context handle
Returns:	Joint_radian: the joint angle of six joints, unit: radian
	Success: 0

23. Remove all the set global waypoints

Name:	remove_all_waypoint()
Function:	Remove all the set global waypoints
Parameters:	
Returns:	Joint_radian: the joint angle of six joints, unit: radian

24. Add the global waypoint for track movement

Name:	add_waypoint(joint_radian(1.0,1.0,1.0,1.0,1.0,1.0))
Function:	Add the global waypoint for track movement
Parameters:	Joint_radian: the joint angle of six joints, unit: radian
Returns:	Success: 0
	Fail: other

25. The track movement of the robot

Name:	move_track(track_type)
Function:	After adding the waypoint by using add_waypoint, proceed the track movement
Parameters:	track_type: type of the track movement Arc movement: RobotMoveTrackType.ARC_CIR Track movement: RobotMoveTrackType.CARTESIAN_MOVEP
Track movement type:	2:ARC_CIR At least 3 points, circle or arc, use circular number to separate, 0 is arc, greater than 0 is circle. 3:CARTESIAN_MOVEP At least 3 points, must to set blend radius, The blend radius must be less than 1/2 of the length of the shortest line segment, and the speed should not be high The following methods are not available: The following four kinds of three-order spline interpolation curves have the beginning and end point acceleration discontinuities, not available for the new joint drive version 4:CARTESIAN_CUBICSPLINE Cubic spline interpolation (over control point), automatically optimize the track running time. Changing attitude is currently not available. 5:CARTESIAN_UBSPLINEINTP It is necessary to set the time interval of cubic uniform b-spline interpolation (over control points). Changing attitude is currently not available. 6:JOINT_CUBICSPLINE 7:JOINT_UBSPLINEINTP Used for track playback
Returns:	Success: 0
	Fail: other

26. Set the blend radius

Name:	set_blend_radius(blend_radius=0.01)
Function:	Set the blend radius, unit: meter
Parameters:	blend_radius : blend radius, unit(m)
Returns:	Result:
	Success: 0
	Fail: other

27. Set the times of the circular movement

Name:	set_circular_loop_times(circular_count=1)
Function:	Set the times of the circular movement
Parameters:	When circular_count is greater than 0, the robot is proceeding circular movement circular_count times. When circular_count is equal to 0, the robot is proceeding arc track movement.
Returns:	Result:
	Success: 0
	Fail: other

28. Set the user coordinate system

Name:	set_user_coord(user_coord)
Function:	Set the user coordinate system
Parameters:	<p> RSHD context handle user_coord user coordinate system user_coord = {'coord_type': 2, coordinate system type: must be 2, assign the user coordinate system 'calibrate_method': 0, coordinate system calibration method 'calibrate_points': coordinate system calibration point {"point1": (0.0, 0.0, 0.0, 0.0, 0.0, 0.0), "point2": (0.0, 0.0, 0.0, 0.0, 0.0, 0.0), "point3": (0.0, 0.0, 0.0, 0.0, 0.0, 0.0)}, 'tool_desc': tool description {"pos": (0.0, 0.0, 0.0), the tool position corresponding to the terminal coordinate system "ori": (1.0, 0.0, 0.0, 0.0)} the tool attitude corresponding to the terminal coordinate system } </p>
Returns:	Result:
	Success: 0
	Fail: other

29. Set the base coordinate system

Name:	set_base_coord()
Function:	Set the base coordinate system
Parameters:	
Returns:	Result:
	Success: 0
	Fail: other

30. Check whether the user coordinate is reasonable

Name:	check_user_coord(user_coord)
Function:	Set the user coordinate system
Parameters:	user_coord user coordinate system user_coord = {'coord_type': 2, coordinate system type: must be 2, assign the user coordinate system 'calibrate_method': 0, coordinate system calibration method 'calibrate_points': coordinate system calibration point {"point1": (0.0, 0.0, 0.0, 0.0, 0.0, 0.0), "point2": (0.0, 0.0, 0.0, 0.0, 0.0, 0.0), "point3": (0.0, 0.0, 0.0, 0.0, 0.0, 0.0)}, 'tool_desc': tool description {"pos": (0.0, 0.0, 0.0), the tool position corresponding to the terminal coordinate system "ori": (1.0, 0.0, 0.0, 0.0)} the tool attitude corresponding to the terminal coordinate system }
Returns:	Result:
	Success: 0
	Fail: other

31. Set the relative offset on base coordinate system

Name:	set_relative_offset_on_base(relative(x,y,z))
Function:	Set the relative offset on base coordinate system
Parameters:	Relative x,y,z relative shift, unit: meter
Returns:	Result:
	Success: 0
	Fail: other

32. Set the relative offset on user coordinate system

Name:	set_relative_offset_on_user(relative(x,y,z),user_coord)
Function:	Set the relative offset on user coordinate system
Parameters:	RSHD: context handle Relative x,y,z: relative shift, unit: meter user_coord: user coordinate system user_coord = {'coord_type': 2, coordinate system type: must be 2, assign the user coordinate system 'calibrate_method': 0, coordinate system calibration method 'calibrate_points': coordinate system calibration point {"point1": (0.0, 0.0, 0.0, 0.0, 0.0, 0.0), "point2": (0.0, 0.0, 0.0, 0.0, 0.0, 0.0), "point3": (0.0, 0.0, 0.0, 0.0, 0.0, 0.0)}, 'tool_desc': tool description {"pos": (0.0, 0.0, 0.0), the tool position corresponding to the terminal coordinate system "ori": (1.0, 0.0, 0.0, 0.0)} the tool attitude corresponding to the terminal coordinate system }
Returns:	Result:
	Success: 0
	Fail: other

33. Forward kinematics

Name:	forward_kin(joint_radian(1.0,1.0,1.0,1.0,1.0,1.0))
Function:	Forward kinematics
Parameters:	Joint_radian : the joint angle of six joints unit: radian
Returns:	Forward kinematics result: waypoint {'joint': [1.0, 1.0, 1.0, 1.0, 1.0, 1.0], 'pos': [-0.06403157614989634, -0.4185973810159096, 0.816883228463401], 'ori': [-0.11863209307193756, 0.3820514380931854, 0.0, 0.9164950251579285]}

34. Inverse kinematics

Name:	inverse_kin(joint_radian(1.0, 1.0, 1.0, 1.0, 1.0, 1.0), pos(x,y,z), ori(w,x,y,z))
Function:	Inverse kinematics
Parameters:	joint_radian The joint angles of the six joints at the starting point, unit(rad) Pos position information Ori attitude information
Returns:	Result: Success: 0 Fail: other
Forward kinematics result:	waypoint {'joint': [1.0, 1.0, 1.0, 1.0, 1.0, 1.0], 'pos': [-0.06403157614989634, -0.4185973810159096, 0.816883228463401], 'ori': [-0.11863209307193756, 0.3820514380931854, 0.0, 0.9164950251579285]}

35. Convert the base coordinate system to user coordinate system

Name:	base_to_user(pos(x,y,z), ori(w,x,y,z), user_coord, tool(x,y,z))
Function:	Convert the base coordinate system to user coordinate system
Parameters:	<p>Pos (x,y,z): the position information on base coordinate system</p> <p>Ori (w,x,y,z): the attitude information on base coordinate system</p> <p>user_coord: user coordinate system</p> <p>user_coord = {'coord_type': 2, coordinate system type: must be 2, assign the user coordinate system</p> <p> 'calibrate_method': 0, coordinate system calibration method</p> <p> 'calibrate_points': coordinate system calibration point</p> <p> {"point1": (0.0, 0.0, 0.0, 0.0, 0.0, 0.0),</p> <p> "point2": (0.0, 0.0, 0.0, 0.0, 0.0, 0.0),</p> <p> "point3": (0.0, 0.0, 0.0, 0.0, 0.0, 0.0)},</p> <p> 'tool_desc': tool description</p> <p> {"pos": (0.0, 0.0, 0.0), the tool position corresponding to the terminal coordinate system</p> <p> "ori": (1.0, 0.0, 0.0, 0.0)} the tool attitude corresponding to the terminal coordinate system</p> <p> }</p> <p>Tool (pos(x,y,z), ori(w,x,y,z)): the position and attitude of the user tool</p>
Returns:	<p>the position and attitude of the user coordinate system:</p> <p> {"pos":(1,2,3),</p> <p> "ori":(1,2,3,4)}</p>

36. Convert the user coordinate system to base coordinate system

Name:	user_to_base(pos(x,y,z), ori(w,x,y,z), user_coord, tool(x,y,z))
Function:	Convert the user coordinate system to base coordinate system
Parameters:	<p>Pos (x,y,z): the position information on base coordinate system</p> <p>Ori (w,x,y,z): the attitude information on base coordinate system</p> <p>user_coord: user coordinate system</p> <p>user_coord = {'coord_type': 2, coordinate system type: must be 2, assign the user coordinate system</p> <p> 'calibrate_method': 0, coordinate system calibration method</p> <p> 'calibrate_points': coordinate system calibration point</p> <p> {"point1": (0.0, 0.0, 0.0, 0.0, 0.0, 0.0),</p> <p> "point2": (0.0, 0.0, 0.0, 0.0, 0.0, 0.0),</p> <p> "point3": (0.0, 0.0, 0.0, 0.0, 0.0, 0.0)},</p> <p> 'tool_desc': tool description</p> <p> {"pos": (0.0, 0.0, 0.0), the tool position corresponding to the terminal coordinate system</p> <p> "ori": (1.0, 0.0, 0.0, 0.0)} the tool attitude corresponding to the terminal coordinate system</p> <p> }</p> <p>Tool (pos(x,y,z), ori(w,x,y,z)): the position and attitude of the user tool</p>
Returns:	<p>the position and attitude of the base coordinate system:</p> <p> {"pos":(1,2,3),</p> <p> "ori":(1,2,3,4)}</p>

37. Robot startup

Name:	robot_startup(collision, tool_dynamics)
Function:	Robot startup
Parameters:	Collision collision class(0~10) tool_dynamics dynamics parameter {"position": (x, y, z), tool's centre of gravity "payload": 1.5 load, (0~5)kilograms "inertia": (xx,xy,xz,yy,yz,zz) inertia}
Returns:	Result:
	Success: 0
	Fail: other
Startup state of robot:	state 0 ROBOT_SERVICE_READY ready 1 ROBOT_SERVICE_STARTING starting 2 ROBOT_SERVICE_WORKING working 3 ROBOT_SERVICE_CLOSING closing 4 ROBOT_SERVICE_CLOSED closed 5 ROBOT_SETVICE_FAULT_POWER power fault 6 ROBOT_SETVICE_FAULT_BRAKE, brake fault 7 ROBOT_SETVICE_FAULT_NO_ROBOT no robot

38. Shut down the robot

Name:	robot_shutdown()
Function:	Shut down the robot
Parameters:	
Returns:	Result:
	Success: 0
	Fail: other

39. Stop the robot movement

Name:	move_stop()
Function:	Stop the movement of robot
Parameters:	
Returns:	Result:
	Success: 0
	Fail: other

40. Suspend the robot movement

Name:	move_pause()
Function:	Suspend the movement of robot
Parameters:	
Returns:	Result:
	Success: 0
	Fail: other

41. Continue the movement of robot

Name:	move_continue()
Function:	Continue the movement of robot
Parameters:	
Returns:	Result:
	Success: 0
	Fail: other

42. Collision recovery

Name:	collision_recover()
Function:	The recovery after collision
Parameters:	
Returns:	Result:
	Success: 0
	Fail: other

43. Get the service state of the robot

Name:	get_robot_state()
Function:	Get the service state of the robot
Parameters:	
Returns:	Result:
	Success: 0
	Fail: other
Startup the state of robot:	state 0 ROBOT_SERVICE_READY ready 1 ROBOT_SERVICE_STARTING starting 2 ROBOT_SERVICE_WORKING working 3 ROBOT_SERVICE_CLOSING closing 4 ROBOT_SERVICE_CLOSED closed 5 ROBOT_SERVICE_FAULT_POWER power fault 6 ROBOT_SERVICE_FAULT_BRAKE, brake fault 7 ROBOT_SERVICE_FAULT_NO_ROBOT no robot

44. Set the working mode of the robot

Name:	set_work_mode(mode)
Function:	Set the working mode of the robot
Parameters:	Mode 0 simulation mode 1 real robot
Returns:	Result:
	Success: 0
	Fail: other

45. Get the current working mode of the robot

Name:	get_work_mode()
Function:	Get the current working mode of the robot
Parameters:	
Returns:	Mode 0 simulation mode 1 real robot

46. Set the collision class of the robot

Name:	set_collision_class(collision)
Function:	Set the collision class of the robot
Parameters:	Collision collision class(0~10)
Returns:	Result:
	Success: 0

47. Determine whether the real robot has been linked

Name:	is_have_real_robot()
Function:	Determine whether the real robot has been linked
Parameters:	
Returns:	The real robot exists or not
	Not-exist: 0
	Exist :1

48. Get the joint state of the real robot

Name:	get_joint_status()
Function:	Get the joint state of the real robot
Parameters:	
Returns:	Joint state <pre>{'joint1': {'current':current(mA),'voltage':voltage(Volts),'temperature':temperature(Celsius)}, 'joint2':{'current':0,'voltage':0.0,'temperature':0}, 'joint3':{'current':0,'voltage':0.0,'temperature':0}, 'joint4':{'current':0,'voltage':0.0,'temperature':0}, 'joint5':{'current':0,'voltage':0.0,'temperature':0}, 'joint6':{'current':0,'voltage':0.0,'temperature':0}}</pre>

49. Get the I/O configuration of the robot interface board

Name:	get_board_io_config(iotype)
Function:	Get the I/O configuration of the robot interface board
Parameters:	RSHD context handle Iotype: IO type: 0:ControllerDI, 1:ControllerDO, 2:ControllerAI, 3:ControllerAO, 4:UserDI, 5:UserDO, 6:UserAI, 7:UserAO, 8:ToolPower, 9:ToolDI, 10:ToolDO, 11:ToolAI, 12:ToolAO,
Returns:	IO configuration: ({ "id": ID "name": "IO name" "addr": IO address "type": IO type "valu": IO current value}, { "id": ID "name": "IO name" "addr": IO address "type": IO type "valu": IO current value}, ...}

50. Set the I/O state of the robot interface board

Name:	set_board_io_status(Iotype, name, value)
Function:	Set the I/O state of the robot interface board
Parameters:	Iotype: 0:ControllerDI, 1:ControllerDO, 2:ControllerAI, 3:ControllerAO, 4:UserDI, 5:UserDO, 6:UserAI, 7:UserAO, 8:ToolPower, 9:ToolDI, 10:ToolDO, 11:ToolAI, 12:ToolAO Name: IO name Value: IO state
Returns:	Result:
	Success: 0

51. Get the I/O state of the robot interface board

Name:	get_board_io_status(Iotype, name)
Function:	Get the I/O state of the robot interface board
Parameters:	IoType: 0:ControllerDI, 1:ControllerDO, 2:ControllerAI, 3:ControllerAO, 4:UserDI, 5:UserDO, 6:UserAI, 7:UserAO, 8:ToolPower, 9:ToolDI, 10:ToolDO, 11:ToolAI, 12:ToolAO Name: IO name
Returns:	Value:IO state

52. Get the tool power state of the robot

Name:	get_tool_power_type()
Function:	Get the power state of the robot on tool
Parameters:	
Returns:	Power_type: OUT_0V = 0, OUT_12V = 1, OUT_24V = 2

53. Set the tool power state of the robot

Name:	set_tool_power_type(power_type)
Function:	Set the tool power state of the robot
Parameters:	Power_type: OUT_0V = 0, OUT_12V = 1, OUT_24V = 2
Returns:	Result: Success: 0

54. Set the tool I/O type of the robot

Name:	set_tool_io_type(addr, iotype)
Function:	Set the tool I/O type of the robot
Parameters:	Addr: I/O address at the tool TOOL_DIGITAL_IO_0 = 0, TOOL_DIGITAL_IO_1 = 1, TOOL_DIGITAL_IO_2 = 2, TOOL_DIGITAL_IO_3 = 3 IoType: IO type 9:ToolDI, 10:ToolDO, 11:ToolAI, 12:ToolAO
Returns:	Result: Success: 0

55. Get the tool power value of the robot

Name:	get_tool_power_voltage()
Function:	Get the tool power value of the robot
Parameters:	
Returns:	Voltage value: voltage

56. Set the tool I/O state of the robot

Name:	set_tool_io_status(name, status)
Function:	Set the tool I/O state of the robot
Parameters:	Addr: I/O address at tool TOOL_DIGITAL_IO_0 = 0, TOOL_DIGITAL_IO_1 = 1, TOOL_DIGITAL_IO_2 = 2, TOOL_DIGITAL_IO_3 = 3 IoType: IO type 9:ToolDI, 10:ToolDO, 11:ToolAI, 12:ToolAO status:IO data (0 or 1)
Returns:	Result: Success: 0

57. Set the tool I/O state of the robot

Name:	get_tool_io_status(name)
Function:	Get the tool I/O state of the robot
Parameters:	Addr: I/O address at tool TOOL_DIGITAL_IO_0=0, TOOL_DIGITAL_IO_1=1, TOOL_DIGITAL_IO_2=2, TOOL_DIGITAL_IO_3=3 IoType: IO type: 9:ToolDI, 10:ToolDO, 11:ToolAI, 12:ToolAO
Returns:	status:IO data (0 or 1)



58. The robot event callback function

Name:	setcallback_robot_event(robot_event_callback)
Function:	Set the callback function of the robot event
Parameters:	robot_event_callback callback function name under the Python
Returns:	Result: Success: 0

Python callback function parameters	<pre> {'code': event ID, 'type': event type} Event types as shown below : typedef enum{ RobotEvent_armCanbusError, //robot CAN bus error RobotEvent_remoteHalt, //robot stop RobotEvent_remoteEmergencyStop, //robot remote emergency stop RobotEvent_jointError, //joint error RobotEvent_forceControl, //force control RobotEvent_exitForceControl, //quit the force control RobotEvent_softEmergency, //soft scram RobotEvent_exitSoftEmergency, //quit the soft emergency stop RobotEvent_collision, //collision RobotEvent_collisionStatusChanged, //collision status changed RobotEvent_tcpParametersSucc, //tool dynamic parameters set successfully RobotEvent_powerChanged, //the robot power switch state changed RobotEvent_ArmPowerOff, //robot power off RobotEvent_mountingPoseChanged, //the installation location has changed RobotEvent_encoderError, //encoder error RobotEvent_encoderLinesError, //the number of encoders are not equivalent RobotEvent_singularityOverspeed, //singularity overspeed RobotEvent_currentAlarm, //abnormal robot current RobotEvent_toolioError, //robot tool error RobotEvent_robotStartupPhase, //robot startup stage RobotEvent_robotStartupDoneResult, //the result of completing startup RobotEvent_robotShutdownDone, //the result of completing shutdown RobotEvent_atTrackTargetPos, //the signal notification of robot moving to the target position (track movement) RobotSetPowerOnDone, //Setting power state has completed RobotReleaseBrakeDone, //releasing the robot brake has completed RobotEvent_robotControllerStateChaned, //the control state of the robot has changed RobotEvent_robotControllerError, //robot control error----It usually comes back when there are problems with algorithmic planning RobotEvent_socketDisconnected, //socket disconnected RobotEvent_overSpeed, //overspeed RobotEvent_algorithmException, //robot arithmetic exceptions //interface board io event RobotEvent_boardIoPoweron, //external power-on signal RobotEvent_boardIoRunmode, //linkage/manual RobotEvent_boardIoPause, //external pause signal RobotEvent_boardIoStop, //external stop signal RobotEvent_boardIoHalt, //external halt signal RobotEvent_boardIoEmergency, //external emergency stop signal RobotEvent_boardIoRelease_alarm, //external all-clear signal RobotEvent_boardIoOrigin_pose, //external back-to-original position signal RobotEvent_boardIoAutorun, //external autorun signal //interface board safety io event RobotEvent_safetyIoExternalEmergencyStope, //external emergency stop input 01 </pre>
--	--

	<pre> RobotEvent_safetyIoExternalSafeguardStope, //external safeguard stop input 02 RobotEvent_safetyIoReduced_mode, //reduced mode input RobotEvent_safetyIoSafeguard_reset, //reset safeguard RobotEvent_safetyIo3PositionSwitch, //three position switch 1 RobotEvent_safetyIoOperationalMode, //operation mode RobotEvent_safetyIoManualEmergencyStop, //demonstrator emergency stop 01 RobotEvent_safetyIoSystemStop, //system stop input //robot working event RobotEvent_alreadySuspended, //robot suspended RobotEvent_alreadyStopped, //robot stopped RobotEvent_alreadyRunning, //robot running RobotEvent_exceptEvent = 100, //unknown event robot_event_unknown, //user event RobotEvent_User = 1000, // first user event id RobotEvent_MaxUser = 65535 // last user event id }RobotEventType;</pre>
Example	<pre> import libpyaubo5 # robot event def robot_event(event): print(event) # set the robot event callback function libpyaubo5.setcallback_robot_event(robot_event)</pre>